

EastWest Sounds

Hollywood Orchestra - Harp

Articulations - Content

Articulation	Violin
Sus Bisbigliando MOD	
Maestro Bsbglnd MOD	
Angels Bisbigliando MOD	
Pluck Long	
Thumb Pick	
Nail Pick	
Gliss Technique	
Près de la table	
Harmonics	
Double Hit	
Bisbigliando	
FX	
Gliss	
Gliss Angelic Slow	
Sus	
Maestro	
Angels	
Angels Harmonic	
Gliss Angelic Fast	

- Standard Articulations
- Additional Articulations

Unlike the other Hollywood Orchestra presets, this preset preserves the original articulation order from OPUS. The standard articulations are enabled by default in the player and are highlighted in light grey on KSEM's Articulation Pad. Enable additional articulations as needed.

Sliders

MIDI CC	Controls
1	Mod: Crossfades or blends between articulations when „MOD“ is included in the articulation name.
5	Legato Time
11	Expression
36	Repetition: RR Reset
64	Repetition: Sustain
65	Portamento
68	Legato
69	Repetition Script
define	Envelope Attack
define	Envelope Decay
define	Envelope Sustain
define	Envelope Release

MIDI CC	Mixer
7	Midi Master
10	Global Pan
define	Close
define	Mid
define	Main
define	Surround
define	Vintage
define	Mood Mix Preset
define	Reverb


Many other parameters can be assigned to MIDI CCs. I've only listed the most common ones, for which you'll also find matching slider names in KSEM.

EastWest Sounds


Hollywood Orchestra - Opus

How to




The presets have been created using the default keyswitch assignments provided in OPUS. You can therefore load the standard instruments. **Enable** the desired articulation (1) and select **Key** as the trigger method (2). The **default keyswitch** will then be displayed automatically (3). The **same value** is entered in KSEM (4). I chose a velocity of 120, but any velocity value from 1 to 127 will work.



However, I recommend using the exported OPUS instruments included in the **_KSEM Hollywood** folder. This saves you from configuring everything manually and also avoids a few known issues with the Hollywood instruments. For example, *Round Robin* cannot be reset using the default CC36 assignment, and some instruments (such as *2 Trombones EXP*, *2 Trumpets*, and *Low Brass*) contain duplicate keyswitch assignments.



To use the instruments, simply copy the **_KSEM Hollywood** folder into the **Hollywood Strings Opus Instruments** directory, located where your Hollywood Orchestra sample library is installed (5). If you're not sure where that is, you can **right-click** a folder in the OPUS Browser and choose **Show In Desktop** to open its location (6). Finally, click **Refresh Browser** in OPUS (7).



That's it. Have fun making music!