

EastWest Sounds

Hollywood Orchestra - Solo Strings (Violin & Cello)

Articulations - Content and Consistency

Articulation	Violin	Cello
Leg Slur		
Leg Slur Sus		
Leg BC		
Leg BC		
Leg BC Fast		
Leg BC Smooth		
Leg Run		
Leg VB Lyric		
Leg VB Expr		
Sus NV		
Sus NV NV VB XF		
Sus NV VB VB XF		
Sus VB		
Sus VB Expr		
Sus VB Lyric		
Sus Flaut		
Détaché		
Martelé		
Marc Short		
Marc Lng		
Spic		
Pizz		
Sfz		
Trem		

■ Common Articulations
■ Additional Articulations

The preset comes in two versions.

The Consistent Layout keeps unavailable articulation slots empty, allowing you to copy and paste automation envelopes between the two instruments.

Sliders

MIDI CC	Controls
1	Mod: Dynamic, Vibrato, HT/WT, Up/Down
5	Legato Time
11	Expression
15	Con Sordino (Mute)
22	True Legato Mono
36	Repetition: RR Reset
64	Repetition: Sustain
65	Portamento
68	Legato
69	Repetition Script
define	Envelope Attack
define	Envelope Decay
define	Envelope Sustain
define	Envelope Release

MIDI CC	Mixer
7	Midi Master
10	Global Pan
define	Close
define	Mid
define	Main
define	Surround
define	Vintage
define	Mood Mix Preset
define	Reverb


Many other parameters can be assigned to MIDI CCs. I've only listed the most common ones, for which you'll also find matching slider names in KSEM.

EastWest Sounds


Hollywood Orchestra - Opus

How to




The presets have been created using the default keyswitch assignments provided in OPUS. You can therefore load the standard instruments. **Enable** the desired articulation (1) and select **Key** as the trigger method (2). The **default keyswitch** will then be displayed automatically (3). The **same value** is entered in KSEM (4). I chose a velocity of 120, but any velocity value from 1 to 127 will work.



However, I recommend using the exported OPUS instruments included in the **_KSEM Hollywood** folder. This saves you from configuring everything manually and also avoids a few known issues with the Hollywood instruments. For example, *Round Robin* cannot be reset using the default CC36 assignment, and some instruments (such as *2 Trombones EXP*, *2 Trumpets*, and *Low Brass*) contain duplicate keyswitch assignments.



To use the instruments, simply copy the **_KSEM Hollywood** folder into the **Hollywood Strings Opus Instruments** directory, located where your Hollywood Orchestra sample library is installed (5). If you're not sure where that is, you can **right-click** a folder in the OPUS Browser and choose **Show In Desktop** to open its location (6). Finally, click **Refresh Browser** in OPUS (7).



That's it. Have fun making music!